
pyPAHdb Documentation

Release 0.5.0a1

Christiaan Boersma and Matthew J. Shannon

Mar 13, 2018

CONTENTS:

1	Introduction	1
2	pypahdb package	3
2.1	Subpackages	3
2.2	Submodules	4
2.3	pypahdb.decomposer module	4
2.4	pypahdb.observation module	4
2.5	pypahdb.spectrum module	5
2.6	pypahdb.writer module	5
2.7	Module contents	5
3	Indices and tables	7
	Python Module Index	9
	Index	11

INTRODUCTION

This is the Nasa Ames...

PYPAHDB PACKAGE

2.1 Subpackages

2.1.1 pypahdb.tests package

Submodules

pypahdb.tests.test_observation module

test_observation.py: unit tests for class observation.

```
class pypahdb.tests.test_observation.SpectrumTestCase (methodName='runTest')  
    Bases: unittest.case.TestCase  
  
    Unit tests for observation.py  
  
    test_is_instance()  
        Can we create an instance of observation?
```

pypahdb.tests.test_spectrum module

test_spectrum.py: unit tests for class spectrum.

```
class pypahdb.tests.test_spectrum.SpectrumTestCase (methodName='runTest')  
    Bases: unittest.case.TestCase  
  
    Unit tests for spectrum.py  
  
    test_convert_units_micron_to_wavenumber()  
        Can we correctly convert micron to wavenumber?  
  
    test_is_instance()  
        Can we create an instance of spectrum?
```

pypahdb.tests.test_writer module

test_writer.py: unit tests for class writer.

```
class pypahdb.tests.test_writer.WriterTestCase (methodName='runTest')  
    Bases: unittest.case.TestCase  
  
    Unit tests for writer.py
```

```
test_is_instance()
```

Can we create an instance of writer?

Module contents

unit tests for pypahdb

2.2 Submodules

2.3 pypahdb.decomposer module

decomposer.py: Using a precomputed matrix of theoretically calculated PAH emission spectra a spectrum is decomposed into contribution PAH subclasses using a nnls-approach.

This file is part of pypahdb - see the module docs for more information.

```
class pypahdb.decomposer.decomposer(spectrum)
    Bases: object

    Decomposes a spectrum with PAHdb.

    spectrum
        The decomposed spectrum.

    fit
        Return the fitted spectra.

        Returns returns array

    ionized_fraction
        Return the ionized fraction.

        Returns returns array

    large_fraction
        Return the large fraction.

        Returns returns array
```

2.4 pypahdb.observation module

observation.py: Holds and astronomical observation

This file is part of pypahdb - see the module docs for more information.

```
class pypahdb.observation.observation(file_path)
    Bases: object

    Create an observation object for later analysis.

    Currently setup to read ASCII data.

    spectrum
        spectrum – contains loaded spectrum
```


2.5 pypahdb.spectrum module

spectrum.py: Holds a spectrum

This file is part of pypahdb - see the module docs for more information.

class pypahdb.spectrum.**spectrum**(*abscissa, ordinate, uncertainties, units*)

Bases: object

Create a spectrum object.

abscissa

numpy.ndarray – The abscissa values.

ordinate

numpy.ndarray – The ordinate values.

uncertainties

numpy.ndarray – Uncertainties on the ordinate.

units

list – The units.

convertunitsto(***keywords*)

Convert units.

Parameters

- **aunits** (*str*) – The new abscissa units.
- **ounits** (*str*) – The new ordinate units.

Returns Nothing.

2.6 pypahdb.writer module

writer.py: Writes decomposer results to file

This file is part of pypahdb - see the module docs for more information.

class pypahdb.writer.**writer**(*result, header="", basename=""*)

Bases: object

Creates a writer object.

Writes PDF and FITS files.

Attributes:

2.7 Module contents

The pyPAHdb module: Using a precomputed matrix of theoretically calculated PAH emission spectra from the NASA Ames PAH IR Spectroscopic Database a spectrum is decomposed into contribution PAH subclasses using a nnls-approach.

pyPAHdb uses a precomputed matrix of theoretically calculated PAH emission spectra from version 3.00 of the library of computed spectra. This matrix has been constructed from a collection of “astronomical” PAHs, which meet the following criteria and include the fullerenes C60 and C70:

`'magnesium=0 oxygen=0 iron=0 silicium=0 chx=0 ch2=0 c>20 hydrogen>0'`

The PAH emission spectra have been calculated with the following parameters:

- A calculated vibrational temperature upon the absorption of a 7 eV photon
- Blackbody emission at the calculated vibrational temperature
- A redshift of 15 /cm to mimic some anharmonic effect
- Gaussian emission profile with a FWHM of 15 /cm

The NASA Ames PAH IR Spectroscopic Database website is located at www.astrochemistry.org/pahdb/.

You are kindly asked to cite the following papers when using pyPAHdb:

- C. Boersma, C.W. Bauschlicher, Jr., A. Ricca, A.L. Mattioda, J. Cami, E. Peeters, F. Sanchez de Armas, G. Puerta Saborido, D.M. Hudgins, and L.J. Allamandola, "THE NASA AMES PAH IR SPECTROSCOPIC DATABASE VERSION 2.00: UPDATED CONTENT, WEBSITE AND ON/OFFLINE TOOLS", The Astrophysical Journal Supplement Series, 211, 8, 2014 10.1088/0067-0049/211/1/8
- C.W. Bauschlicher, Jr., C. Boersma, A. Ricca, A.L. Mattioda, J. Cami, E. Peeters, F. Sanchez de Armas, G. Puerta Saborido, D.M. Hudgins, and L.J. Allamandola, "THE NASA AMES PAH IR SPECTROSCOPIC DATABASE: THE COMPUTED SPECTRA", The Astrophysical Journal Supplement Series, 189, 341, 2010 10.1088/0067-0049/189/2/341
- Mattioda, A. L., Hudgins, D. M., Boersma, C., Ricca, A., Peeters, E., Cami, J., Sanchez de Armas, F., Puerta Saborido, G., Bauschlicher, C. W., J., and Allamandola, L. J. "THE NASA AMES PAH IR SPECTROSCOPIC DATABASE: THE LABORATORY SPECTRA", The Astrophysical Journal Supplement Series, XXX, 201X (in preparation)

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

PYTHON MODULE INDEX

p

- `pypahdb`, 5
- `pypahdb.decomposer`, 4
- `pypahdb.observation`, 4
- `pypahdb.spectrum`, 5
- `pypahdb.tests`, 4
- `pypahdb.tests.test_observation`, 3
- `pypahdb.tests.test_spectrum`, 3
- `pypahdb.tests.test_writer`, 3
- `pypahdb.writer`, 5

INDEX

A

abscissa (pypahdb.spectrum.spectrum attribute), 5

C

convertunitsto() (pypahdb.spectrum.spectrum method), 5

D

decomposer (class in pypahdb.decomposer), 4

F

fit (pypahdb.decomposer.decomposer attribute), 4

I

ionized_fraction (pypahdb.decomposer.decomposer attribute), 4

L

large_fraction (pypahdb.decomposer.decomposer attribute), 4

O

observation (class in pypahdb.observation), 4

ordinate (pypahdb.spectrum.spectrum attribute), 5

P

pypahdb (module), 5

pypahdb.decomposer (module), 4

pypahdb.observation (module), 4

pypahdb.spectrum (module), 5

pypahdb.tests (module), 4

pypahdb.tests.test_observation (module), 3

pypahdb.tests.test_spectrum (module), 3

pypahdb.tests.test_writer (module), 3

pypahdb.writer (module), 5

S

spectrum (class in pypahdb.spectrum), 5

spectrum (pypahdb.decomposer.decomposer attribute), 4

spectrum (pypahdb.observation.observation attribute), 4

SpectrumTestCase (class in pypahdb.tests.test_observation), 3

SpectrumTestCase (class in pypahdb.tests.test_spectrum), 3

T

test_convert_units_micron_to_wavenumber() (pypahdb.tests.test_spectrum.SpectrumTestCase method), 3

test_is_instance() (pypahdb.tests.test_observation.SpectrumTestCase method), 3

test_is_instance() (pypahdb.tests.test_spectrum.SpectrumTestCase method), 3

test_is_instance() (pypahdb.tests.test_writer.WriterTestCase method), 3

U

uncertainties (pypahdb.spectrum.spectrum attribute), 5

units (pypahdb.spectrum.spectrum attribute), 5

W

writer (class in pypahdb.writer), 5

WriterTestCase (class in pypahdb.tests.test_writer), 3